

2. Message Structure Chart .....	4
3. Branching Diagram.....	6
4. Segments Description .....	11
5. Segments Layout.....	15
6. Example(s) .....	67

## 1. Introduction

---

30/06/17

## 2. Message Structure Chart

---

### Arrival Notice Heading Section

UNH	1	M	1	- Message header
BGM	2	M	1	- Beginning of message
DTM	3	C	9	- Date/time/period
TSR	4	C	9	- Transport service requirements
MOA	5	C	99	- Monetary amount
FTX	6	C	99	- Free text
CNT	7	C	9	- Control total
SG1		C	99	- LOC
LOC	8	M	1	- Place/location identification
SG3		C	99	- RFF-DTM
RFF	9	M	1	- Reference
DTM	10	C	9	- Date/time/period
SG8		C	99	- TDT-DTM-SG9
TDT	11	M	1	- Details of transport
DTM	12	C	9	- Date/time/period
SG9		C	99	- LOC
LOC	13	M	1	- Place/location identification
SG11		C	99	- NAD-SG12-SG15
NAD	14	M	1	- Name and address
SG12		C	9	- CTA-COM
CTA	15	M	1	- Contact information
COM	16	C	9	- Communication contact
SG15		C	9	- RFF
RFF	17	M	1	- Reference

### Arrival Notice Detail Section

SG18		C	999	- GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30
GID	18	M	1	- Goods item details
TMP	19	C	1	- Temperature
RNG	20	C	1	- Range details
FTX	21	C	9	- Free text
SG19		C	9	- NAD-DTM
NAD	22	M	1	- Name and address
DTM	23	C	1	- Date/time/period
SG20		C	99	- MEA-EQN
MEA	24	M	1	- Measurements
EQN	25	C	1	- Number of units
SG21		C	99	- DIM-EQN
DIM	26	M	1	- Dimensions
EQN	27	C	1	- Number of units
SG22		C	9	- RFF
RFF	28	M	1	- Reference
SG23		C	9	- PCI-GIN
PCI	29	M	1	- Package identification
GIN	30	C	9	- Goods identity number
SG27		C	999	- SGP
SGP	31	M	1	- Split goods placement
SG30		C	99	- DGS-FTX-SG31-SG32
DGS	32	M	1	- Dangerous goods
FTX	33	C	99	- Free text
SG31		C	9	- CTA-COM
CTA	34	M	1	- Contact information
COM	35	C	9	- Communication contact
SG32		C	9	- MEA-EQN
MEA	36	M	1	- Measurements
EQN	37	C	1	- Number of units
SG35		C	999	- EQD-MEA-DIM-SEL-SG37

## 2. Message Structure Chart

---


EQD	38	M	1	- Equipment details
MEA	39	C	9	- Measurements
DIM	40	C	9	- Dimensions
SEL	41	C	99	- Seal number
SG37		C	9	- NAD
NAD	42	M	1	- Name and address

### Arrival Notice Summary Section

UNT	43	M	1	- Message trailer
-----	----	---	---	-------------------


### 3. Branching Diagram

---




### 3. Branching Diagram

---




### 3. Branching Diagram

---




### 3. Branching Diagram

---



### 3. Branching Diagram

---



## 4. Segments Description

---

### Arrival Notice Heading Section

UNH - M 1	- Message header This segment is used to head, identify and specify a message.
BGM - M 1	- Beginning of message This segment is used to indicate the type and function of a message and to transmit the identifying number.
DTM - C 9	- Date/time/period This segment is used to specify any dates related to the arrival notice message.
TSR - C 9	- Transport service requirements This segment is used to indicate the party responsible for the unloading of the goods from the transport means at the arrival location.
MOA - C 99	- Monetary amount This segment is used to specify monetary values related to the arriving consignment.
FTX - C 99	- Free text This segment is used to provide free form or coded text information related to the entire message.
CNT - C 9	- Control total This segment is used to provide application data for message control purposes.
<b>SG1</b> - C 99	- <b>LOC</b> A group of segments to specify locations which apply to the entire message, e.g. place of transhipment.
LOC - M 1	- Place/location identification This segment is used to identify any locations related to the complete arriving consignment.
<b>SG3</b> - C 99	- <b>RFF-DTM</b> A group of segments containing a reference and constants which apply to the entire message.
RFF - M 1	- Reference This segment is used to specify references relating to the consignment arriving.
DTM - C 9	- Date/time/period This segment is used to specify any dates related to the previous RFF segment.
<b>SG8</b> - C 99	- <b>TDT-DTM-SG9</b> A group of segments to indicate details of the movement of goods such as mode and means of transport, locations, departure, and arrival date(s) and time(s).
TDT - M 1	- Details of transport This segment is used to indicate the main carriage transport means, and where necessary, the exact identification of the transport used for the arriving consignment.
DTM - C 9	- Date/time/period This segment is used to specify any dates relating to the transport specified in the previous TDT segment.
<b>SG9</b> - C 99	- <b>LOC</b> A group of segments to specify a location related to this leg of transport.
LOC - M 1	- Place/location identification This segment is used to identify any locations related to the transport details previously specified.

## 4. Segments Description

---

<b>SG11 - C 99</b>	<b>- NAD-SG12-SG15</b>
	A group of segments to identify a party, related references and contacts for the complete message.
<b>NAD - M 1</b>	<b>- Name and address</b>
	This segment is used to identify the parties involved in the arrival notice message. Identification of the consignor and/or consignee, and/or the carrier or forwarder is mandatory in the arrival notice message.
<b>SG12 - C 9</b>	<b>- CTA-COM</b>
	A group of segments identifying a contact and its communications related to the party.
<b>CTA - M 1</b>	<b>- Contact information</b>
	This segment is used to identify department and contact names within the company specified in the NAD segment.
<b>COM - C 9</b>	<b>- Communication contact</b>
	This segment identifies the communications number and type of communications for the person or department identified in the preceding CTA segment.
<b>SG15 - C 9</b>	<b>- RFF</b>
	A group of segments to specify a reference related to the party.
<b>RFF - M 1</b>	<b>- Reference</b>
	This segment is used to identify any references related to the party identified in the NAD segment.

### Arrival Notice Detail Section

<b>SG18 - C 999</b>	<b>- GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30</b>
	A group of segments to describe the goods items for which transport is undertaken.
<b>GID - M 1</b>	<b>- Goods item details</b>
	This segment is the trigger segment for the detail section of the arrival notice message. It is used to specify the type of packaging for the goods item(s) which are contained in the arriving consignment.
<b>TMP - C 1</b>	<b>- Temperature</b>
	This segment is used to specify transport temperature settings related to the current goods item.
<b>RNG - C 1</b>	<b>- Range details</b>
	This segment is used to specify transport temperature ranges related to the goods item.
<b>FTX - C 9</b>	<b>- Free text</b>
	This segment is used to provide free form or coded text information related to the entire message.
<b>SG19 - C 9</b>	<b>- NAD-DTM</b>
	A group of segments to identify different places of collection and/or delivery for the goods item.
<b>NAD - M 1</b>	<b>- Name and address</b>
	This segment is used to specify the place of delivery for the current goods item.
<b>DTM - C 1</b>	<b>- Date/time/period</b>
	This DTM segment is used to specify dates and times relating to the delivery party specified in the preceding NAD segment.
<b>SG20 - C 99</b>	<b>- MEA-EQN</b>
	A group of segments to specify measurements applicable to a goods item.

## 4. Segments Description

---

MEA - M 1	<ul style="list-style-type: none"> <li>- Measurements</li> </ul> <p>This segment is used to specify a measurement for the goods identified in the GID segment. All measurements given in the MEA segments relate to the highest level of packaging (the despatch units) identified in the GID segment.</p>
EQN - C 1	<ul style="list-style-type: none"> <li>- Number of units</li> </ul> <p>This segment is used to specify the number of packages (despatch units) within the goods item to which the measurement applies.</p>
<b>SG21 - C 99</b>	<ul style="list-style-type: none"> <li>- <b>DIM-EQN</b></li> </ul> <p>A group of segments to specify dimensions applicable to a goods item.</p>
DIM - M 1	<ul style="list-style-type: none"> <li>- Dimensions</li> </ul> <p>This segment is used to indicate the dimensions of the goods item identified in the GID segment. All dimensions given in the DIM segments relate to the highest level packaging (the despatch units) identified in the GID segment.</p>
EQN - C 1	<ul style="list-style-type: none"> <li>- Number of units</li> </ul> <p>This segment is used to specify the number of packages (despatch units) within the goods items to which the dimensions apply.</p>
<b>SG22 - C 9</b>	<ul style="list-style-type: none"> <li>- <b>RFF</b></li> </ul> <p>A group of segments to identify references to a goods item.</p>
RFF - M 1	<ul style="list-style-type: none"> <li>- Reference</li> </ul> <p>This segment is used to specify references which are applicable to the current goods item only. The references specified here override any specified in segment group 03 in the header.</p>
<b>SG23 - C 9</b>	<ul style="list-style-type: none"> <li>- <b>PCI-GIN</b></li> </ul> <p>A group of segments to specify marks and numbers of a goods item.</p>
PCI - M 1	<ul style="list-style-type: none"> <li>- Package identification</li> </ul> <p>This segment is used to specify markings and labels on the goods item.</p>
GIN - C 9	<ul style="list-style-type: none"> <li>- Goods identity number</li> </ul> <p>This segment is used to provide identification numbers marked on the packaging of the current goods item.</p>
<b>SG27 - C 999</b>	<ul style="list-style-type: none"> <li>- <b>SGP</b></li> </ul> <p>A group of segments to specify the distribution of a goods item among the transport equipment.</p>
SGP - M 1	<ul style="list-style-type: none"> <li>- Split goods placement</li> </ul> <p>This segment is used to specify the placement of the goods item in the equipment used for the arriving consignment.</p>
<b>SG30 - C 99</b>	<ul style="list-style-type: none"> <li>- <b>DGS-FTX-SG31-SG32</b></li> </ul> <p>A group of segments to specify dangerous goods details related to the goods item. One goods item may be in different dangerous goods classes.</p>
DGS - M 1	<ul style="list-style-type: none"> <li>- Dangerous goods</li> </ul> <p>This segment is used to indicate whether the goods item in the arriving consignment contains any dangerous goods.</p>
FTX - C 99	<ul style="list-style-type: none"> <li>- Free text</li> </ul> <p>This segment is used to specify any additional information required for the dangerous goods.</p>
<b>SG31 - C 9</b>	<ul style="list-style-type: none"> <li>- <b>CTA-COM</b></li> </ul> <p>A group of segments to identify a contact to whom communication regarding the dangerous goods can be directed.</p>

## 4. Segments Description

---

CTA - M 1	- Contact information  This segment is used to identify a contact name relating to the dangerous goods identified in the DGS segment.
COM - C 9	- Communication contact  This segment identifies the communications number and type of communications for the person or department identified in the preceding CTA segment.
<b>SG32 - C 9</b>	<b>- MEA-EQN</b>  A group of segments to identify dangerous goods measurements.
MEA - M 1	- Measurements  This segment is used to indicate measurements of the goods item which are dangerous.
EQN - C 1	- Number of units  This segment is used to indicate the number of units to which the dangerous goods measurements apply.
<b>SG35 - C 999</b>	<b>- EQD-MEA-DIM-SEL-SG37</b>  A group of segments to specify equipment in which goods are transported.
EQD - M 1	- Equipment details  This segment is used to indicate the units of equipment which have been used for the transport of the goods items in the arriving consignment.
MEA - C 9	- Measurements  This segment is used to specify the gross or tare weight of the equipment identified in the previous EQD segment.
DIM - C 9	- Dimensions  This segment is used to indicate the dimensions of the equipment identified in the EQD segment.
SEL - C 99	- Seal number  This segment is used to specify a seal number for the equipment identified in the EQD segment.
<b>SG37 - C 9</b>	<b>- NAD</b>  A group of segments to identify different equipment pick-up or drop-off places.
NAD - M 1	- Name and address  This segment is used to specify the equipment owner, pick up or drop off addresses for the equipment specified in the EQD segment.

### Arrival Notice Summary Section

UNT - M 1	- Message trailer  This segment is used to end and check the completeness of a message.
-----------	---

## 5. Segments Layout

This section describes each segment used in the EANCOM® Arrival notice message. The original EDIFACT segment layout is listed. The appropriate comments relevant to the EANCOM® subset are indicated.

### Notes:

1. The segments are presented in the sequence in which they appear in the message. The segment or segment group tag is followed by the (M)andatory / (C)onditional indicator, the maximum number of occurrences and the segment description.
2. Reading from left to right, in column one, the data element tags and descriptions are shown, followed by in the second column the EDIFACT status (M or C), the field format, and the picture of the data elements. These first pieces of information constitute the original EDIFACT segment layout.

Following the EDIFACT information, EANCOM® specific information is provided in the third, fourth, and fifth columns. In the third column a status indicator for the use of (C)onditional EDIFACT data elements (see 2.1 through 2.3 below), in the fourth column the restricted indicator (see point 3 on the following page), and in the fifth column notes and code values used for specific data elements in the message.

- 2.1 (M)andatory data elements in EDIFACT segments retain their status in EANCOM®.
- 2.2 Additionally, there are five types of status for data elements with a (C)onditional EDIFACT status, whether for simple, component or composite data elements. These are listed below and can be identified when relevant by the following abbreviations:

- REQUIRED	R	Indicates that the entity is required and must be sent.
- ADVISED	A	Indicates that the entity is advised or recommended.
- DEPENDENT	D	Indicates that the entity must be sent in certain conditions, as defined by the relevant explanatory note.
- OPTIONAL	O	Indicates that the entity is optional and may be sent at the discretion of the user.
- NOT USED	N	Indicates that the entity is not used and should be omitted.

- 2.3 If a composite is flagged as **N, NOT USED**, all data elements within that composite will have blank status indicators assigned to them.

3. Status indicators detailed in the fourth column which directly relate to the code values detailed in the fifth **column** may have two values:

- RESTRICTED	*	A data element marked with an asterisk (*) in the fourth column indicates that the listed codes in column five are the only codes available for use with this data element, in this segment, in this message.
- OPEN		All data elements where coded representation of data is possible and a restricted set of code values is not indicated are open (no asterisk in fourth column). The available codes are listed in the EANCOM® Data Elements and Code Sets Directory. Code values may be given as examples or there may be a note on the format or type of code to be used.

4. Different colours are used for the code values in the segment details: restricted codes are in red and open codes in blue.

## 5. Segments Layout

Segment number: 1

<b>UNH</b>	- M	1 - Message header						
Function:								
To head, identify and specify a message.								
	EDIFACT	GS1	*	Description				
0062 Message reference number	M an..14	<b>M</b>		Senders unique message reference. Sequence number of the messages in the interchange. DE 0062 in the UNT will be identical. Sender generated.				
S009 MESSAGE IDENTIFIER	M	<b>M</b>						
0065 Message type	M an..6	<b>M</b>	*	IFTMAN = Arrival notice message				
0052 Message version number	M an..3	<b>M</b>	*	D = Draft version/UN/EDIFACT Directory				
0054 Message release number	M an..3	<b>M</b>	*	01B = Release 2001 - B				
0051 Controlling agency	M an..2	<b>M</b>	*	UN = UN/CEFACT				
0057 Association assigned code	C an..6	<b>R</b>	*	EAN003 = GS1 version control number (GS1 Permanent Code)				
				Indicates that the message is the EANCOM version 003 of the UNSM Arrival Notice message.				
0068 Common access reference	C an..35	<b>N</b>						
S010 STATUS OF THE TRANSFER	C	<b>N</b>						
0070 Sequence of transfers	M n..2							
0073 First and last transfer	C a1							
Segment Notes:								
This segment is used to head, identify and specify a message.								
DE's 0065, 0052, 0054, and 0051: Indicate that the message is a UNSM Arrival Notice message based on the D.01B directory under the control of the United Nations.								
Example: UNH+ME000001+IFTMAN:D:01B:UN:EAN003'								

## 5. Segments Layout

Segment number: 2

<b>BGM</b>	- M	1 - Beginning of message			
Function:					
To indicate the type and function of a message and to transmit the identifying number.					
		EDIFACT	GS1	*	Description
C002	DOCUMENT/MESSAGE NAME	C	R		
1001	Document name code	C an..3	R	*	781 = Arrival notice (goods) 78E = Proof of delivery (GS1 Temporary Code)
1131	Code list identification code	C an..17	N		
3055	Code list responsible agency code	C an..3	D	*	9 = GS1 This data element is only used if the GS1 code value 78E is used in data element 1001.
1000	Document name	C an..35	O		
C106	DOCUMENT/MESSAGE IDENTIFICATION	C	R		
1004	Document identifier	C an..35	R		Arrival notice number assigned by the document sender. For global unique identification of documents Global Document Type Identifier (GDTI) is available.
1056	Version identifier	C an..9	N		
1060	Revision identifier	C an..6	N		
1225	Message function code	C an..3	R	*	5 = Replace 9 = Original 31 = Copy The message function, coded is a critical data element in this segment. It applies to all data indicated in the message. The following definitions apply for the restricted codes: 5 = Replace - Cancel the original arrival notice and replace with this arrival notice (original arrival notice reference is specified in RFF SG3). 9 = Original - An original transmission of a arrival notice. 31 = Copy - Copy of the arrival notice for a third party for information purposes.
4343	Response type code	C an..3	N		
Segment Notes:					
This segment is used to indicate the type and function of a message and to transmit the identifying number. All references other than the document number DE 1004 are to be put in the RFF segment.					
Example: BGM+781+52188+9'					

## 5. Segments Layout

Segment number: 3

<b>DTM</b> - C 9 - Date/time/period					
Function:					
To specify date, and/or time, or period.					
		EDIFACT	GS1	*	Description
C507	DATE/TIME/PERIOD	M	<b>M</b>		
2005	Date or time or period function code qualifier	M an..3	<b>M</b>	*	<p>2 = Delivery date/time, requested          17 = Delivery date/time, estimated          58 = Clearance date (Customs)          137 = Document/message date/time          143 = Acceptance date/time of goods          151 = Importation date</p>
2380	Date or time or period value	C an..35	<b>R</b>		
2379	Date or time or period format code	C an..3	<b>R</b>		<p>102 = CCYYMMDD          203 = CCYYMMDDHHMM          718 = CCYYMMDD-CCYYMMDD</p>
Segment Notes:					
This segment is used to specify any dates related to the arrival notice message. DE 2005: Identification of the 'Document/message date/time' (code value 137) is mandatory in an EANCOM message.					
Example: DTM+137:20021201:102'					

## 5. Segments Layout

Segment number: 4

TSR - C 9 - Transport service requirements				
Function: To specify the contract and carriage conditions and service and priority requirements for the transport.				
	EDIFACT	GS1	*	Description
C536 CONTRACT AND CARRIAGE CONDITION	C	N		
4065 Contract and carriage condition code	M an..3			
1131 Code list identification code	C an..17			
3055 Code list responsible agency code	C an..3			
C233 SERVICE	C	O		
7273 Service requirement code	M an..3	M		13 = <a href="#">Carrier unloads</a> 15 = <a href="#">Consignee unloads</a>
1131 Code list identification code	C an..17	O		
3055 Code list responsible agency code	C an..3	D		
7273 Service requirement code	C an..3	O		
1131 Code list identification code	C an..17	O		
3055 Code list responsible agency code	C an..3	D		
C537 TRANSPORT PRIORITY	C	N		
4219 Transport service priority code	M an..3			
1131 Code list identification code	C an..17			
3055 Code list responsible agency code	C an..3			
C703 NATURE OF CARGO	C	N		
7085 Cargo type classification code	M an..3			
1131 Code list identification code	C an..17			
3055 Code list responsible agency code	C an..3			
Segment Notes:				
This segment is used to indicate the party responsible for the unloading of the goods from the transport means at the arrival location.				
Example: TSR++13'				

## 5. Segments Layout

Segment number: 5

MOA - C 99 - Monetary amount				
Function: To specify a monetary amount.				
	EDIFACT	GS1	*	Description
C516 MONETARY AMOUNT	M	<b>M</b>		
5025 Monetary amount type code qualifier	M an..3	<b>M</b>		22 = <a href="#">Cash on delivery amount</a> 50 = <a href="#">Disbursements</a>
5004 Monetary amount	C n..35	<b>R</b>		
6345 Currency identification code	C an..3	<b>O</b>		
6343 Currency type code qualifier	C an..3	<b>N</b>		
4405 Status description code	C an..3	<b>N</b>		

Segment Notes:  
This segment is used to specify monetary values related to the arriving consignment.

Example:  
MOA+22:100'

## 5. Segments Layout

Segment number: 6

FTX - C 99 - Free text				
Function:				
To provide free form or coded text information.				
	EDIFACT	GS1	*	Description
4451 Text subject code qualifier	M an..3	<b>M</b>		AAI = General information BLR = Transport document remarks DAR = Damage remarks NAI = Non-acceptance information (GS1 Temporary Code)
4453 Free text function code	C an..3	<b>O</b>		1 = Text for subsequent use
C107 TEXT REFERENCE	C	<b>D</b>		This composite is only used when trading partners have agreed to use mutually defined code values.
4441 Free text value code	M an..17	<b>M</b>		
1131 Code list identification code	C an..17	<b>O</b>		
3055 Code list responsible agency code	C an..3	<b>D</b>		87 = Assigned by carrier 91 = Assigned by supplier or supplier's agent 92 = Assigned by buyer or buyer's agent
C108 TEXT LITERAL	C	<b>D</b>		This composite is only used if coded text can not be used.
4440 Free text value	M an..512	<b>M</b>		
4440 Free text value	C an..512	<b>O</b>		
4440 Free text value	C an..512	<b>O</b>		
4440 Free text value	C an..512	<b>O</b>		
4440 Free text value	C an..512	<b>O</b>		
3453 Language name code	C an..3	<b>D</b>		ISO 639 two alpha code This data element is only used when non coded free text has been provided in data element C108.
4447 Free text format code	C an..3	<b>N</b>		
Segment Notes:				
This segment is used to provide free form or coded text information related to the entire message. Use of this segment in free form is not recommended since it may inhibit automatic processing of the arrival notice message. Coded references to standard texts is an available functionality which enables automatic processing and reduces transmission overheads. Standard texts should be mutually defined between trading partners and can be used to cover legal or other requirements.				
Example: FTX+AAI+1+008::87' e.g. Standard text code 008 = 'Goods arriving require additional handling services.'				

## 5. Segments Layout

Segment number: 7

CNT - C 9 - Control total				
Function: To provide control total.				
	EDIFACT	GS1	*	Description
C270 CONTROL	M	<b>M</b>		
6069 Control total type code qualifier	M an..3	<b>M</b>		7 = Total gross weight 11 = Total number of packages 15 = Total consignment, cube 16 = Total number of equipment
6066 Control total value	Mn..18	<b>M</b>		
6411 Measurement unit code	C an..3	<b>O</b>		

Segment Notes:  
This segment is used to provide application data for message control purposes.

Example:  
CNT+11:450'  
When using code value '11' the total specified in data element 6066 is arrived at by adding the values specified only in the first occurrence of C213, data element 7224, of the GID segment.

## 5. Segments Layout

Segment number: 8

<b>SG1</b>	- C	99 - LOC			
<b>LOC</b>	- M	1 - Place/location identification			
Function:					
To identify a place or a location and/or related locations.					
	EDIFACT	GS1	*	Description	
3227 Location function code qualifier	M an..3	<b>M</b>		7 = Place of delivery 10 = Place of acceptance 57 = Place of payment	
C517 LOCATION IDENTIFICATION	C	<b>A</b>			
3225 Location name code	C an..25	<b>A</b>		GLN - Format n13	
1131 Code list identification code	C an..17	<b>O</b>			
3055 Code list responsible agency code	C an..3	<b>D</b>		9 = <b>GS1</b> DE 3055 must be used if DE 3225 is used and does not contain an UN/LOCODE.	
3224 Location name	C an..256	<b>O</b>			
C519 RELATED LOCATION ONE IDENTIFICATION	C	<b>N</b>			
3223 First related location name code	C an..25				
1131 Code list identification code	C an..17				
3055 Code list responsible agency code	C an..3				
3222 First related location name	C an..70				
C553 RELATED LOCATION TWO IDENTIFICATION	C	<b>N</b>			
3233 Second related location name code	C an..25				
1131 Code list identification code	C an..17				
3055 Code list responsible agency code	C an..3				
3232 Second related location name	C an..70				
5479 Relation code	C an..3	<b>N</b>			
Segment Notes:					
This segment is used to identify any locations related to the complete arriving consignment.					
Example: LOC+10+5412345678908::9					

## 5. Segments Layout

Segment number: 9

<b>SG3</b>	- C	99 - RFF-DTM		
<b>RFF</b>	- M	1 - Reference		
Function:				
To specify a reference.				
	EDIFACT	GS1	*	Description
C506 REFERENCE	M	<b>M</b>		
1153 Reference code qualifier	Man..3	<b>M</b>		<p>AAS = Transport document number  CT = Contract number  CU = Consignor's reference number  ON = Order number (buyer)  ASI = Proof of delivery reference number  UCN = Unique consignment reference number</p> <p>The code ASI is a code allocated by the recipient of the goods to confirm to the carrier/consignor successful receipt. This code should only be used when the message is being used for proof of delivery purposes.</p>
1154 Reference identifier	C an..70	<b>R</b>		
1156 Document line identifier	C an..6	<b>N</b>		
4000 Reference version identifier	C an..35	<b>N</b>		
1060 Revision identifier	C an..6	<b>N</b>		
Segment Notes:				
This segment is used to specify references relating to the consignment arriving.				
Example: RFF+CT:76214'				

## 5. Segments Layout

Segment number: 10

<b>SG3</b>	- C	99 - RFF-DTM		
<b>DTM</b>	- C	9 - Date/time/period		
Function:				
To specify date, and/or time, or period.				
	EDIFACT	GS1	*	Description
C507 DATE/TIME/PERIOD	M	<b>M</b>		
2005 Date or time or period function code qualifier	M an..3	<b>M</b>	*	171 = Reference date/time
2380 Date or time or period value	C an..35	<b>R</b>		
2379 Date or time or period format code	C an..3	<b>R</b>		102 = CCYYMMDD 203 = CCYYMMDDHHMM
Segment Notes:				
This segment is used to specify any dates related to the previous RFF segment.				
Example: DTM+171:20021125:102'				

## 5. Segments Layout

---

Segment number: 11

<b>SG8</b>	- C	99 - TDT-DTM-SG9						
<b>TDT</b>	- M	1 - Details of transport						
Function:								
To specify the transport details such as mode of transport, means of transport, its conveyance reference number and the identification of the means of transport.								
		EDIFACT	GS1	*	Description			
8051	Transport stage code qualifier	M an..3	<b>M</b>	*	20 = <b>Main-carriage transport</b>			
8028	Means of transport journey identifier	C an..17	<b>O</b>	Reference number covering the transport.				
C220	MODE OF TRANSPORT	C	<b>A</b>					
8067	Transport mode name code	C an..3	<b>O</b>	10 = 20 = 30 = 40 = 60 =				
8066	Transport mode name	C an..17	<b>N</b>					
C228	TRANSPORT MEANS	C	<b>O</b>	Data Elements 8179 and 8178 are only used when the type of transport must be specifically identified, that is, a generic description such as road transport is unsuitable.				
8179	Transport means description code	C an..8	<b>D</b>	23 = <b>Rail bulk car</b> 31 = <b>Truck</b>				
8178	Transport means description	C an..17	<b>D</b>					
C040	CARRIER	C	<b>O</b>					
3127	Carrier identifier	C an..17	<b>A</b>	GLN - Format n13				
1131	Code list identification code	C an..17	<b>O</b>					
3055	Code list responsible agency code	C an..3	<b>D</b>	9 = <b>GS1</b>				
3128	Carrier name	C an..35	<b>O</b>					
8101	Transit direction indicator code	C an..3	<b>N</b>					
C401	EXCESS TRANSPORTATION INFORMATION	C	<b>N</b>					
8457	Excess transportation reason code	M an..3						
8459	Excess transportation responsibility code	M an..3						
7130	Customer shipment authorisation identifier	C an..17						
C222	TRANSPORT IDENTIFICATION	C	<b>O</b>					
8213	Transport means identification name identifier	C an..9	<b>O</b>					
1131	Code list identification code	C an..17	<b>O</b>					
3055	Code list responsible agency code	C an..3	<b>D</b>	DE 3055 must be used if DE 8213 is used.				
8212	Transport means identification name	C an..35	<b>R</b>	Vehicle license plate/Aircraft number.				

## 5. Segments Layout

---

Segment number: 11

		EDIFACT	GS1	*	Description
8453	Transport means nationality code	C an..3	<b>O</b>		ISO 3166 two alpha code
8281	Transport means ownership indicator code	C an..3	<b>N</b>		

### Segment Notes:

This segment is used to indicate the main carriage transport means, and where necessary, the exact identification of the transport used for the arriving consignment.

### Example:

TDT+20++30+31'

## 5. Segments Layout

Segment number: 12

<b>SG8</b>	- C	99 - TDT-DTM-SG9		
<b>DTM</b>	- C	9 - Date/time/period		
Function:				
To specify date, and/or time, or period.				
	EDIFACT	GS1	*	Description
C507 DATE/TIME/PERIOD	M	<b>M</b>		
2005 Date or time or period function code qualifier	M an..3	<b>M</b>	*	132 = <b>Arrival date/time, estimated</b> 186 = <b>Departure date/time, actual</b>
2380 Date or time or period value	C an..35	<b>R</b>		
2379 Date or time or period format code	C an..3	<b>R</b>		102 = <b>CCYYMMDD</b> 203 = <b>CCYYMMDDHHMM</b> 718 = <b>CCYYMMDD-CCYYMMDD</b>
Segment Notes:				
This segment is used to specify any dates relating to the transport specified in the previous TDT segment.				
Example: DTM+132:200212151000:203'				

## 5. Segments Layout

Segment number: 13

<b>SG8</b>	- C	99 - TDT-DTM-SG9	
<b>SG9</b>	- C	99 - LOC	
<b>LOC</b>	- M	1 - Place/location identification	
Function:			
To identify a place or a location and/or related locations.			
	EDIFACT	GS1 *	Description
3227 Location function code qualifier	M an..3	<b>M</b>	<p>5 = Place of departure          8 = Place of destination          9 = Place/port of loading          11 = Place/port of discharge</p>
C517 LOCATION IDENTIFICATION	C	<b>A</b>	
3225 Location name code	C an..25	<b>A</b>	GLN - Format n13
1131 Code list identification code	C an..17	<b>O</b>	
3055 Code list responsible agency code	C an..3	<b>D</b>	<p>9 = <b>GS1</b>          DE 3055 must be used if DE 3225 is used and does not contain an UN/LOCODE.</p>
3224 Location name	C an..256	<b>O</b>	
C519 RELATED LOCATION ONE IDENTIFICATION	C	<b>N</b>	
3223 First related location name code	C an..25		
1131 Code list identification code	C an..17		
3055 Code list responsible agency code	C an..3		
3222 First related location name	C an..70		
C553 RELATED LOCATION TWO IDENTIFICATION	C	<b>N</b>	
3233 Second related location name code	C an..25		
1131 Code list identification code	C an..17		
3055 Code list responsible agency code	C an..3		
3232 Second related location name	C an..70		
5479 Relation code	C an..3	<b>N</b>	
Segment Notes:			
This segment is used to identify any locations related to the transport details previously specified.			
Example: LOC+5+5412345678908::9'			

## 5. Segments Layout

Segment number: 14

<b>SG11</b>	- C	99 - NAD-SG12-SG15			
<b>NAD</b>	- M	1 - Name and address			
Function:					
To specify the name/address and their related function, either by C082 only and/or unstructured by C058 or structured by C080 thru 3207.					
	EDIFACT	GS1	*	Description	
3035 Party function code qualifier	M an..3	<b>M</b>		CA = Carrier CN = Consignee CZ = Consignor DP = Delivery party FP = Freight/charges payer FW = Freight forwarder NI = Notify party	
C082 PARTY IDENTIFICATION DETAILS	C	<b>A</b>			
3039 Party identifier	M an..35	<b>M</b>		For identification of parties it is recommended to use GLN - Format n13.	
1131 Code list identification code	C an..17	<b>N</b>			
3055 Code list responsible agency code	C an..3	<b>R</b>	*	9 = GS1	
C058 NAME AND ADDRESS	C	<b>O</b>		This composite may only be used to fulfill the requirements of directive 2003/58/EC, article 4.	
3124 Name and address description	M an..35	<b>M</b>			
3124 Name and address description	C an..35	<b>O</b>			
3124 Name and address description	C an..35	<b>O</b>			
3124 Name and address description	C an..35	<b>O</b>			
3124 Name and address description	C an..35	<b>O</b>			
C080 PARTY NAME	C	<b>D</b>			
3036 Party name	M an..35	<b>M</b>		Party Name in clear text.	
3036 Party name	C an..35	<b>O</b>			
3036 Party name	C an..35	<b>O</b>			
3036 Party name	C an..35	<b>O</b>			
3036 Party name	C an..35	<b>O</b>			
3045 Party name format code	C an..3	<b>O</b>			
C059 STREET	C	<b>D</b>			
3042 Street and number or post office box identifier	M an..35	<b>M</b>		Building Name/Number and Street	
3042 Street and number or post office box identifier	C an..35	<b>O</b>		Name and/or P.O. Box	
3042 Street and number or post office box identifier	C an..35	<b>O</b>			
3042 Street and number or post office box identifier	C an..35	<b>O</b>			
3164 City name	C an..35	<b>D</b>		City/Town, clear text.	
C819 COUNTRY SUB-ENTITY DETAILS	C	<b>D</b>			

## 5. Segments Layout

Segment number: 14

		EDIFACT	GS1	*	Description
3229	Country sub-entity name code	C an..9	<b>O</b>		
1131	Code list identification code	C an..17	<b>O</b>		
3055	Code list responsible agency code	C an..3	<b>O</b>		
3228	Country sub-entity name	C an..70	<b>O</b>		County/State, clear text.
3251	Postal identification code	C an..17	<b>D</b>		Postal Code
3207	Country name code	C an..3	<b>D</b>		ISO 3166 two alpha code

### Segment Notes:

This segment is used to identify the parties involved in the arrival notice message. Identification of the consignor and/or consignee, and/or the carrier or forwarder is mandatory in the arrival notice message.

### Example:

NAD+CZ+5411234512309::9'

NAD+FW+5412345123453::9'

### Dependency Notes:

The following composites and data elements are only used when a coded name and address can not be used.

The affected composites and data elements are as follows:

C080 - C059 - 3164 - C819 - 3251 - 3207

## 5. Segments Layout

Segment number: 15

<b>SG11</b>	- C	99 - NAD-SG12-SG15		
<b>SG12</b>	- C	9 - CTA-COM		
<b>CTA</b>	- M	1 - Contact information		
Function:				
To identify a person or a department to whom communication should be directed.				
	EDIFACT	GS1	*	Description
3139 Contact function code	C an..3	<b>R</b>		IC = <a href="#">Information contact</a>
C056 DEPARTMENT OR EMPLOYEE DETAILS	C	<b>O</b>		
3413 Department or employee name code	C an..17	<b>O</b>		
3412 Department or employee name	C an..35	<b>O</b>		
Segment Notes:				
This segment is used to identify department and contact names within the company specified in the NAD segment.				
Example: CTA+IC+:R PAX'				

## 5. Segments Layout

Segment number: 16

<b>SG11</b>	- C	99 - NAD-SG12-SG15		
<b>SG12</b>	- C	9 - CTA-COM		
<b>COM</b>	- C	9 - Communication contact		
Function:				
To identify a communication number of a department or a person to whom communication should be directed.				
	EDIFACT	GS1	*	Description
C076 COMMUNICATION CONTACT	M	<b>M</b>		
3148 Communication address identifier	Man..512	<b>M</b>		
3155 Communication address code qualifier	Man..3	<b>M</b>		EM = <a href="#">Electronic mail</a> TE = <a href="#">Telephone</a> WWW = <a href="#">WWW-Site (EAN Code)</a>
Segment Notes:				
This segment identifies the communications number and type of communications for the person or department identified in the preceding CTA segment.				
Example: COM+0033148759632:FX'				

## 5. Segments Layout

Segment number: 17

<b>SG11</b>	- C	99 - NAD-SG12-SG15		
<b>SG15</b>	- C	9 - RFF		
<b>RFF</b>	- M	1 - Reference		
Function:				
To specify a reference.				
	EDIFACT	GS1	*	Description
C506 REFERENCE	M	<b>M</b>		
1153 Reference code qualifier	M an..3	<b>M</b>	*	YC1 = Additional party identification (GS1 Temporary Code) GN = Government reference number VA = VAT registration number XA = Company/place registration number
1154 Reference identifier	C an..70	<b>R</b>		
1156 Document line identifier	C an..6	<b>N</b>		
4000 Reference version identifier	C an..35	<b>N</b>		
1060 Revision identifier	C an..6	<b>N</b>		
Segment Notes:				
This segment is used to identify any references related to the party identified in the NAD segment.				
Example:				
RFF+YC1:6532'				

## 5. Segments Layout

Segment number: 18

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30						
<b>GID</b>	- M	1 - Goods item details						
Function:								
To indicate totals of a goods item.								
	EDIFACT	GS1	*	Description				
1496 Goods item number	C n..5	R		Application generated number of the item lines within the arrival notice.				
C213 NUMBER AND TYPE OF PACKAGES	C	R						
7224 Package quantity	C n..8	R						
7065 Package type description code	C an..17	O		CT = PK = 09 = Returnable pallet (GS1 Temporary Code) 201 = Pallet ISO 1 - 1/1 EURO Pallet (GS1 Temporary Code)				
1131 Code list identification code	C an..17	N						
3055 Code list responsible agency code	C an..3	D *		9 = GS1				
7064 Type of packages	C an..35	N						
7233 Packaging related description code	C an..3	N						
C213 NUMBER AND TYPE OF PACKAGES	C	O						
7224 Package quantity	C n..8	R						
7065 Package type description code	C an..17	O		CT = PK = 09 = Returnable pallet (GS1 Temporary Code) 201 = Pallet ISO 1 - 1/1 EURO Pallet (GS1 Temporary Code)				
1131 Code list identification code	C an..17	N						
3055 Code list responsible agency code	C an..3	D *		9 = GS1				
7064 Type of packages	C an..35	N						
7233 Packaging related description code	C an..3	N						
C213 NUMBER AND TYPE OF PACKAGES	C	O						
7224 Package quantity	C n..8	R						
7065 Package type description code	C an..17	O		CT = PK = 09 = Returnable pallet (GS1 Temporary Code) 201 = Pallet ISO 1 - 1/1 EURO Pallet (GS1 Temporary Code)				
1131 Code list identification code	C an..17	N						
3055 Code list responsible agency code	C an..3	D *		9 = GS1				

## 5. Segments Layout

Segment number: 18

		EDIFACT	GS1	*	Description
7064	Type of packages	C an..35	N		
7233	Packaging related description code	C an..3	N		
C213	NUMBER AND TYPE OF PACKAGES	C	O		
7224	Package quantity	C n..8	R		
7065	Package type description code	C an..17	O		CT = PK = 09 = <a href="#">Returnable pallet (GS1 Temporary Code)</a> 201 = <a href="#">Pallet ISO 1 - 1/1 EURO Pallet (GS1 Temporary Code)</a>
1131	Code list identification code	C an..17	N		
3055	Code list responsible agency code	C an..3	D *		9 = <a href="#">GS1</a>
7064	Type of packages	C an..35	N		
7233	Packaging related description code	C an..3	N		
C213	NUMBER AND TYPE OF PACKAGES	C	O		
7224	Package quantity	C n..8	R		
7065	Package type description code	C an..17	O		CT = PK = 09 = <a href="#">Returnable pallet (GS1 Temporary Code)</a> 201 = <a href="#">Pallet ISO 1 - 1/1 EURO Pallet (GS1 Temporary Code)</a>
1131	Code list identification code	C an..17	N		
3055	Code list responsible agency code	C an..3	D *		9 = <a href="#">GS1</a>
7064	Type of packages	C an..35	N		
7233	Packaging related description code	C an..3	N		

### Segment Notes:

This segment is the trigger segment for the detail section of the arrival notice message. It is used to specify the type of packaging for the goods item(s) which are contained in the arriving consignment.

Within the GID segment it is possible to identify up to 3 levels of packaging hierarchy for the transport goods item. The top level (first occurrence of C213) identifies the despatch unit.

### Example:

GID+1+1:09::9+6:CT'

(The top level is 1 returnable pallet with a second level containing 6 cartons.)

### Dependency notes:

DE 3055: This data element is only used with the code value '9' if the Type of Packages identified in data element 7065 is an GS1 code.

Hinweis:

## 5. Segments Layout

Segment number: 19

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>TMP</b>	- C	1 - Temperature		
Function:				
To specify the temperature setting.				
	EDIFACT	GS1	*	Description
6245 Temperature type code qualifier	M an..3	<b>M</b>	*	2 = Transport temperature
C239 TEMPERATURE SETTING	C	<b>R</b>		
6246 Temperature value	C n..15	<b>O</b>		
6411 Measurement unit code	C an..3	<b>O</b>		CEL = degree celsius FAH = degree Fahrenheit KEL = kelvin
Segment Notes:				
This segment is used to specify transport temperature settings related to the current goods item.				
Example: TMP+2+40:CEL'				

## 5. Segments Layout

Segment number: 20

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>RNG</b>	- C	1 - Range details		
Function:				
To identify a range.				
	EDIFACT	GS1	*	Description
6167 Range type code qualifier	M an..3	<b>M</b>	*	5 = <b>Temperature range</b>
C280 RANGE	C	<b>R</b>		
6411 Measurement unit code	M an..3	<b>M</b>		CEL = <b>degree celsius</b> FAH = <b>degree Fahrenheit</b> KEL = <b>kelvin</b>
6162 Range minimum value	C n..18	<b>O</b>		
6152 Range maximum value	C n..18	<b>O</b>		
Segment Notes:				
This segment is used to specify transport temperature ranges related to the goods item.				
Example: RNG+5+CEL:4:10'				

## 5. Segments Layout

Segment number: 21

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>FTX</b>	- C	9 - Free text	
Function:			
To provide free form or coded text information.			
	EDIFACT	GS1 *	Description
4451 Text subject code qualifier	M an..3	<b>M</b>	AAA = Goods description DAR = Damage remarks MIS = Missing goods remarks (GS1 Temporary Code) NAI = Non-acceptance information (GS1 Temporary Code)
4453 Free text function code	C an..3	<b>O</b>	1 = Text for subsequent use
C107 TEXT REFERENCE	C	<b>D</b>	This composite is only used when trading partners have agreed to use mutually defined code values.
4441 Free text value code	M an..17	<b>M</b>	
1131 Code list identification code	C an..17	<b>O</b>	
3055 Code list responsible agency code	C an..3	<b>D</b>	87 = Assigned by carrier 91 = Assigned by supplier or supplier's agent 92 = Assigned by buyer or buyer's agent
C108 TEXT LITERAL	C	<b>D</b>	This composite is only used if coded text can not be used.
4440 Free text value	M an..512	<b>M</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
3453 Language name code	C an..3	<b>D</b>	ISO 639 two alpha code This data element is only used when non coded free text has been provided in data element C108.
4447 Free text format code	C an..3	<b>N</b>	
Segment Notes:			
This segment is used to provide free form or coded text information related to the entire message. Use of this segment in free form is not recommended since it may inhibit automatic processing of the arrival notice message. Coded references to standard texts is an available functionality which enables automatic processing and reduces transmission overheads. Standard texts should be mutually defined between trading partners and can be used to cover legal or other requirements.			
Example:			
FTX+DAR+1+012::87'			
(Code value 012 = Goods item damaged by carrier during un-loading at destination.)			

## 5. Segments Layout

---

Segment number: 22

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG19</b>	- C	9 - NAD-DTM	
<b>NAD</b>	- M	1 - Name and address	
Function:			
To specify the name/address and their related function, either by C082 only and/or unstructured by C058 or structured by C080 thru 3207.			
	EDIFACT	GS1 *	Description
3035 Party function code qualifier	M an..3	<b>M</b> *	DP = <b>Delivery party</b>
C082 PARTY IDENTIFICATION DETAILS	C	<b>A</b>	
3039 Party identifier	M an..35	<b>M</b>	For identification of parties it is recommended to use GLN - Format n13.
1131 Code list identification code	C an..17	<b>N</b>	
3055 Code list responsible agency code	C an..3	<b>R</b> *	9 = <b>GS1</b>
C058 NAME AND ADDRESS	C	<b>O</b>	This composite may only be used to fulfill the requirements of directive 2003/58/EC, article 4.
3124 Name and address description	M an..35	<b>M</b>	
3124 Name and address description	C an..35	<b>O</b>	
3124 Name and address description	C an..35	<b>O</b>	
3124 Name and address description	C an..35	<b>O</b>	
3124 Name and address description	C an..35	<b>O</b>	
C080 PARTY NAME	C	<b>D</b>	
3036 Party name	M an..35	<b>M</b>	Party Name in clear text.
3036 Party name	C an..35	<b>O</b>	
3036 Party name	C an..35	<b>O</b>	
3036 Party name	C an..35	<b>O</b>	
3036 Party name	C an..35	<b>O</b>	
3045 Party name format code	C an..3	<b>O</b>	
C059 STREET	C	<b>D</b>	
3042 Street and number or post office box identifier	M an..35	<b>M</b>	Building Name/Number and Street
3042 Street and number or post office box identifier	C an..35	<b>O</b>	Name and/or P.O. Box
3042 Street and number or post office box identifier	C an..35	<b>O</b>	
3042 Street and number or post office box identifier	C an..35	<b>O</b>	
3164 City name	C an..35	<b>D</b>	City/Town, clear text.
C819 COUNTRY SUB-ENTITY DETAILS	C	<b>D</b>	
3229 Country sub-entity name code	C an..9	<b>O</b>	
1131 Code list identification code	C an..17	<b>O</b>	
3055 Code list responsible agency	C an..3	<b>O</b>	

## 5. Segments Layout

Segment number: 22

	EDIFACT	GS1	*	Description
code				
3228 Country sub-entity name	C an..70	<b>O</b>		County/State, clear text.
3251 Postal identification code	C an..17	<b>D</b>		Postal Code
3207 Country name code	C an..3	<b>D</b>		ISO 3166 two alpha code

### Segment Notes:

This segment is used to specify the place of delivery for the current goods item.

Only one occurrence of this segment is allowed per arriving goods item.

### Example:

NAD+DP+5412345123453::9'

### Dependency Notes:

The following composites and data elements are only used when a coded name and address can not be used.

The affected composites and data elements are as follows:

C080 - C059 - 3164 - C819 - 3251 - 3207

## 5. Segments Layout

Segment number: 23

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>SG19</b>	- C	9 - NAD-DTM		
<b>DTM</b>	- C	1 - Date/time/period		
Function:				
To specify date, and/or time, or period.				
	EDIFACT	GS1	*	Description
C507 DATE/TIME/PERIOD	M	<b>M</b>		
2005 Date or time or period function code qualifier	M an..3	<b>M</b>	*	2 = <b>Delivery date/time, requested</b> 17 = <b>Delivery date/time, estimated</b> 58 = <b>Clearance date (Customs)</b> 151 = <b>Importation date</b>
2380 Date or time or period value	C an..35	<b>R</b>		
2379 Date or time or period format code	C an..3	<b>R</b>		102 = <b>CCYYMMDD</b> 203 = <b>CCYYMMDDHHMM</b>
Segment Notes:				
This DTM segment is used to specify dates and times relating to the delivery party specified in the preceding NAD segment.				
Example: DTM+17:20021220:102'				

## 5. Segments Layout

Segment number: 24

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG20</b>	- C	99 - MEA-EQN	
<b>MEA</b>	- M	1 - Measurements	
Function:			
To specify physical measurements, including dimension tolerances, weights and counts.			
	EDIFACT	GS1 *	Description
6311 Measurement purpose code qualifier	M an..3	<b>M</b>	<p>AAE = <a href="#">Measurement</a>          AAI = <a href="#">Item weight</a>          LMT = <a href="#">Loading metre</a></p>
C502 MEASUREMENT DETAILS	C	<b>A</b>	
6313 Measured attribute code	C an..3	<b>A</b>	<p>AAB = <a href="#">Unit gross weight</a>          AAW = <a href="#">Gross volume</a>          G = <a href="#">Gross weight</a>          AFF = <a href="#">Gross measure cube</a>          PMC = <a href="#">Package net measurement cube (GS1 Temporary Code)</a>          T = <a href="#">Tare weight</a></p> <p>This qualifier determines the measurement value to be applied either to one single despatch unit of the goods item or to a number of despatch units of the goods item.</p> <p>When Unit Gross Weight is provided in this segment the measurement provided relates to the total gross weight of one single despatch unit in the goods item. The number of despatch units of the goods item that all have the same quoted gross weight is specified in the EQN segment when different from the number of despatch units specified in the GID segment.</p> <p>When Gross Weight is provided the measurement relates to the total gross weight of a number of despatch units in the goods item. The number of despatch units of the goods item that together have the quoted gross weight is specified in the EQN segment when different to the number of despatch units specified in the GID segment.</p>
6321 Measurement significance code	C an..3	<b>O</b>	<p>3 = <a href="#">Approximately</a>          4 = <a href="#">Equal to</a></p>
6155 Non-discrete measurement name code	C an..17	<b>N</b>	
6154 Non-discrete measurement name	C an..70	<b>N</b>	
C174 VALUE/RANGE	C	<b>R</b>	
6411 Measurement unit code	M an..3	<b>M</b>	<p>KGM = <a href="#">kilogram</a>          LTR = <a href="#">litre</a>          MTR = <a href="#">metre</a>          MTQ = <a href="#">cubic metre</a>          TNE = <a href="#">tonne (metric ton)</a></p>
6314 Measurement value	C an..18	<b>O</b>	
6162 Range minimum value	C n..18	<b>O</b>	
6152 Range maximum value	C n..18	<b>O</b>	
6432 Significant digits quantity	C n..2	<b>N</b>	

## **5. Segments Layout**

---

7383	Surface or layer code	C an..3	N		
------	-----------------------	---------	---	--	--

## **5. Segments Layout**

---

Segment number: 24

**Segment Notes:**

This segment is used to specify a measurement for the goods identified in the GID segment. All measurements given in the MEA segments relate to the highest level of packaging (the despatch units) identified in the GID segment.

**Example:**

MEA+AAI+G+KGM:1600'

## 5. Segments Layout

Segment number: 25

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30
<b>SG20</b>	- C	99 - MEA-EQN
<b>EQN</b>	- C	1 - Number of units

Function:

To specify the number of units.

		EDIFACT	GS1	*	Description
C523	NUMBER OF UNIT DETAILS	M	<b>M</b>		
6350	Units quantity	C n..15	<b>R</b>		
6353	Unit type code qualifier	C an..3	<b>N</b>		

Segment Notes:

This segment is used to specify the number of packages (despatch units) within the goods item to which the measurement applies.

Example:

EQN+1'

## 5. Segments Layout

Segment number: 26

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG21</b>	- C	99 - DIM-EQN	
<b>DIM</b>	- M	1 - Dimensions	
Function:			
To specify dimensions.			
	EDIFACT	GS1 *	Description
6145 Dimension type code qualifier	M an..3	<b>M</b> *	<p>1 = Gross dimensions 10E = Unit gross dimensions (GS1 Temporary Code)</p> <p>This qualifier determines the dimension values to be applied either to one single despatch unit of the goods item or to a number of despatch units of the goods item.</p> <p>When Unit Gross Dimensions are provided in this segment the dimension values provided relate to the total gross dimensions of one single despatch unit in the goods item. The number of despatch units of the goods item that all have the same quoted gross dimensions is specified in the EQN segment when different from the number of despatch units specified in the GID segment.</p> <p>When Gross Dimensions are provided the dimension values relate to the total gross weight of a number of despatch units in the goods item. The number of despatch units of the goods item that together have the quoted gross dimension is specified in the EQN segment when different to the number of despatch units specified in the GID segment.</p>
C211 DIMENSIONS	M	<b>M</b>	
6411 Measurement unit code	M an..3	<b>M</b>	MTR = metre
6168 Length dimension value	C n..15	<b>O</b>	
6140 Width dimension value	C n..15	<b>O</b>	
6008 Height dimension value	C n..15	<b>O</b>	
Segment Notes:			
This segment is used to indicate the dimensions of the goods item identified in the GID segment. All dimensions given in the DIM segments relate to the highest level packaging (the despatch units) identified in the GID segment.			
Example: DIM+1+MTR:4:2:2'			

## 5. Segments Layout

Segment number: 27

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG21</b>	- C	99 - DIM-EQN	
<b>EQN</b>	- C	1 - Number of units	
Function:			
To specify the number of units.			
	EDIFACT	GS1 *	Description
C523 NUMBER OF UNIT DETAILS	M	<b>M</b>	
6350 Units quantity	C n..15	<b>R</b>	The value expressed in this data element must be the sum of all the values of DE 7224 in the first occurrence of C213 in the GID segment throughout the message.
6353 Unit type code qualifier	C an..3	<b>N</b>	
Segment Notes:			
This segment is used to specify the number of packages (despatch units) within the goods items to which the dimensions apply.			
Example: EQN+22'			

## 5. Segments Layout

Segment number: 28

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>SG22</b>	- C	9 - RFF		
<b>RFF</b>	- M	1 - Reference		
Function:				
To specify a reference.				
	EDIFACT	GS1	*	Description
C506 REFERENCE	M	<b>M</b>		
1153 Reference code qualifier	M an..3	<b>M</b>		CT = <a href="#">Contract number</a> ON = <a href="#">Order number (buyer)</a>
1154 Reference identifier	C an..70	<b>R</b>		
1156 Document line identifier	C an..6	<b>O</b>		
4000 Reference version identifier	C an..35	<b>N</b>		
1060 Revision identifier	C an..6	<b>N</b>		
Segment Notes:				
This segment is used to specify references which are applicable to the current goods item only. The references specified here override any specified in segment group 03 in the header.				
Example: RFF+CT:52441'				

## 5. Segments Layout

Segment number: 29

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG23</b>	- C	9 - PCI-GIN	
<b>PCI</b>	- M	1 - Package identification	
Function:			
To specify markings and labels on individual packages or physical units.			
	EDIFACT	GS1 *	Description
4233 Marking instructions code	C an..3	<b>R</b>	16 = Buyer's instructions 17 = Supplier's instructions 18 = Carrier's instructions 33E = Marked with serial shipping container code (GS1 Temporary Code)
C210 MARKS & LABELS	C	<b>O</b>	
7102 Shipping marks description	M an..35	<b>M</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
7102 Shipping marks description	C an..35	<b>O</b>	
8275 Container or package contents indicator code	C an..3	<b>N</b>	
C827 TYPE OF MARKING	C	<b>N</b>	
7511 Marking type code	M an..3		
1131 Code list identification code	C an..17		
3055 Code list responsible agency code	C an..3		
Segment Notes:			
This segment is used to specify markings and labels on the goods item.			
Example:			
The packaging for the goods item are marked with the GS1 Serial Shipping Container Code 354123450000000014. PCI+33E'			

## 5. Segments Layout

Segment number: 30

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>SG23</b>	- C	9 - PCI-GIN		
<b>GIN</b>	- C	9 - Goods identity number		
Function:				
To give specific identification numbers, either as single numbers or ranges.				
	EDIFACT	GS1	*	Description
7405 Object identification code qualifier	M an..3	<b>M</b>	*	BJ = <b>Serial shipping container code</b> In EANCOM it is required to use the Serial Shipping Container Code (SSCC's) for unique identification of individual transport packages.
C208 IDENTITY NUMBER RANGE	M	<b>M</b>		
7402 Object identifier	M an..35	<b>M</b>		
7402 Object identifier	C an..35	<b>O</b>		
C208 IDENTITY NUMBER RANGE	C	<b>O</b>		
7402 Object identifier	M an..35	<b>M</b>		
7402 Object identifier	C an..35	<b>O</b>		
C208 IDENTITY NUMBER RANGE	C	<b>O</b>		
7402 Object identifier	M an..35	<b>M</b>		
7402 Object identifier	C an..35	<b>O</b>		
C208 IDENTITY NUMBER RANGE	C	<b>O</b>		
7402 Object identifier	M an..35	<b>M</b>		
7402 Object identifier	C an..35	<b>O</b>		
C208 IDENTITY NUMBER RANGE	C	<b>O</b>		
7402 Object identifier	M an..35	<b>M</b>		
7402 Object identifier	C an..35	<b>O</b>		

Segment Notes:  
This segment is used to provide identification numbers marked on the packaging of the current goods item.

Example:  
GIN+BJ+354123450000000014'

## 5. Segments Layout

Segment number: 31

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30		
<b>SG27</b>	- C	999 - SGP		
<b>SGP</b>	- M	1 - Split goods placement		
Function:				
To specify the placement of goods in relation to equipment.				
	EDIFACT	GS1	*	Description
C237 EQUIPMENT IDENTIFICATION	M	<b>M</b>		
8260 Equipment identifier	C an..17	<b>R</b>		The value in DE 8260 indicates the identity number of the equipment in/on which the goods item is transported.
1131 Code list identification code	C an..17	<b>O</b>		
3055 Code list responsible agency code	C an..3	<b>D</b>		
3207 Country name code	C an..3	<b>O</b>		
7224 Package quantity	C n..8	<b>O</b>		
Segment Notes:				
This segment is used to specify the placement of the goods item in the equipment used for the arriving consignment.				
Example: SGP+45223+1'				

## 5. Segments Layout

Segment number: 32

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>DGS</b>	- M	1 - Dangerous goods	
Function:			
To identify dangerous goods.			
	EDIFACT	GS1 *	Description
8273 Dangerous goods regulations code	C an..3	<b>R</b>	ADR = European agreement regarding the total carriage of dangerous goods CFR = 49 code of federal regulations RID = Rail/road dangerous goods book (RID)
C205 HAZARD CODE	C	<b>O</b>	
8351 Hazard identification code	M an..7	<b>M</b>	Classification according ADR/RID rules
8078 Additional hazard classification identifier	C an..7	<b>O</b>	Additional according ADR/RID rules
8092 Hazard code version identifier	C an..10	<b>O</b>	
C234 UNDG INFORMATION	C	<b>O</b>	
7124 United Nations Dangerous Goods (UNDG) identifier	C n4	<b>O</b>	
7088 Dangerous goods flashpoint value	C an..8	<b>O</b>	Declaration of the flashpoint.
C223 DANGEROUS GOODS SHIPMENT FLASHPOINT	C	<b>O</b>	
7106 Shipment flashpoint value	C n3	<b>O</b>	
6411 Measurement unit code	C an..3	<b>O</b>	CEL = degree celsius
8339 Packaging danger level code	C an..3	<b>O</b>	1 = Great danger 2 = Medium danger 3 = Minor danger
8364 Emergency procedure for ships identifier	C an..6	<b>O</b>	Only for emergency procedure on ships.
8410 Hazard medical first aid guide identifier	C an..4	<b>O</b>	
8126 Transport emergency card identifier	C an..10	<b>O</b>	TREM card number according ADR.
C235 HAZARD IDENTIFICATION PLACARD DETAILS	C	<b>O</b>	
8158 Orange hazard placard upper part identifier	C an..4	<b>O</b>	Danger signs upper part.
8186 Orange hazard placard lower part identifier	C an4	<b>O</b>	Danger signs lower part.
C236 DANGEROUS GOODS LABEL	C	<b>O</b>	According ADR, FID, IMDG-code, IATA-DGR.
8246 Dangerous goods marking identifier	C an..4	<b>O</b>	Number of dangerous goods document primary hazard.
8246 Dangerous goods marking identifier	C an..4	<b>O</b>	Number of dangerous goods document secondary hazard.
8246 Dangerous goods marking identifier	C an..4	<b>O</b>	

## 5. Segments Layout

Segment number: 32

		EDIFACT	GS1	*	Description
8255	Packing instruction type code	C an..3	O		
8325	Hazardous means of transport category code	C an..3	O		Only used by air carrier.
8211	Hazardous cargo transport authorisation code	C an..3	O		

### Segment Notes:

This segment is used to indicate whether the goods item in the arriving consignment contains any dangerous goods.

### Example:

Dangerous goods according to the ADR regulation 3B for extremely flammable liquids with a flashpoint of 21 degrees celsius and a UN number 1178.

DGS+ADR+3B+1178+21.0:CEL'

## 5. Segments Layout

Segment number: 33

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>FTX</b>	- C	99 - Free text	
Function:			
To provide free form or coded text information.			
	EDIFACT	GS1 *	Description
4451 Text subject code qualifier	M an..3	<b>M</b> *	AAC = Dangerous goods additional information AAD = Dangerous goods, technical name
4453 Free text function code	C an..3	<b>O</b>	1 = Text for subsequent use
C107 TEXT REFERENCE	C	<b>D</b>	This composite is only used when trading partners have agreed to use mutually defined code values.
4441 Free text value code	M an..17	<b>M</b>	
1131 Code list identification code	C an..17	<b>O</b>	
3055 Code list responsible agency code	C an..3	<b>D</b>	89 = Assigned by distributor 90 = Assigned by manufacturer 91 = Assigned by supplier or supplier's agent 92 = Assigned by buyer or buyer's agent
C108 TEXT LITERAL	C	<b>D</b>	This composite is only used if coded text can not be used.
4440 Free text value	M an..512	<b>M</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
4440 Free text value	C an..512	<b>O</b>	
3453 Language name code	C an..3	<b>D</b>	ISO 639 two alpha code This data element is only used when non coded free text has been provided in data element C108.
4447 Free text format code	C an..3	<b>N</b>	
Segment Notes:			
This segment is used to specify any additional information required for the dangerous goods. Use of this segment in free form is not recommended since it may inhibit automatic processing of the arrival notice message. Coded references to standard texts is an available functionality which enables automatic processing and reduces transmission overheads. Standard texts should be mutually defined between trading partners and can be used to cover legal or other requirements.			
Example: FTX+AAD+++DIETHYL ACETALDEHYDE'			

## 5. Segments Layout

Segment number: 34

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>SG31</b>	- C	9 - CTA-COM	
<b>CTA</b>	- M	1 - Contact information	
Function:			
To identify a person or a department to whom communication should be directed.			
	EDIFACT	GS1 *	Description
3139 Contact function code	C an..3	<b>R</b>	HE = Emergency dangerous goods contact HG = Dangerous goods contact
C056 DEPARTMENT OR EMPLOYEE DETAILS	C	<b>O</b>	
3413 Department or employee name code	C an..17	<b>O</b>	
3412 Department or employee name	C an..35	<b>O</b>	
Segment Notes:			
This segment is used to identify a contact name relating to the dangerous goods identified in the DGS segment.			
Example: CTA+HG+:J REEVES'			

## 5. Segments Layout

Segment number: 35

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>SG31</b>	- C	9 - CTA-COM	
<b>COM</b>	- C	9 - Communication contact	
Function:			
To identify a communication number of a department or a person to whom communication should be directed.			
	EDIFACT	GS1 *	Description
C076 COMMUNICATION CONTACT	M	<b>M</b>	
3148 Communication address identifier	Man..512	<b>M</b>	
3155 Communication address code qualifier	Man..3	<b>M</b>	EM = <a href="#">Electronic mail</a> TE = <a href="#">Telephone</a> WWW =
Segment Notes:  This segment identifies the communications number and type of communications for the person or department identified in the preceding CTA segment.			
Example: COM+0033148759632:TE'			

## 5. Segments Layout

Segment number: 36

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>SG32</b>	- C	9 - MEA-EQN	
<b>MEA</b>	- M	1 - Measurements	
Function:			
To specify physical measurements, including dimension tolerances, weights and counts.			
	EDIFACT	GS1 *	Description
6311 Measurement purpose code qualifier	M an..3	<b>M</b>	AAE = <a href="#">Measurement</a>
C502 MEASUREMENT DETAILS	C	<b>A</b>	
6313 Measured attribute code	C an..3	<b>A</b>	
6321 Measurement significance code	C an..3	<b>N</b>	
6155 Non-discrete measurement name code	C an..17	<b>N</b>	
6154 Non-discrete measurement name	C an..70	<b>N</b>	
C174 VALUE/RANGE	C	<b>R</b>	
6411 Measurement unit code	M an..3	<b>M</b>	KGM = <a href="#">kilogram</a>
6314 Measurement value	C an..18	<b>O</b>	
6162 Range minimum value	C n..18	<b>O</b>	
6152 Range maximum value	C n..18	<b>O</b>	
6432 Significant digits quantity	C n..2	<b>N</b>	
7383 Surface or layer code	C an..3	<b>N</b>	
Segment Notes:			
This segment is used to indicate measurements of the goods item which are dangerous.			
Example: MEA+AAE+AAF+KGM:500'			

## 5. Segments Layout

Segment number: 37

<b>SG18</b>	- C	999 - GID-TMP-RNG-FTX-SG19-SG20-SG21-SG22-SG23-SG27-SG30	
<b>SG30</b>	- C	99 - DGS-FTX-SG31-SG32	
<b>SG32</b>	- C	9 - MEA-EQN	
<b>EQN</b>	- C	1 - Number of units	
Function:			
To specify the number of units.			
	EDIFACT	GS1 *	Description
C523 NUMBER OF UNIT DETAILS	M	<b>M</b>	
6350 Units quantity	C n..15	<b>R</b>	
6353 Unit type code qualifier	C an..3	<b>O</b>	2 = <a href="#">Transportable unit</a>
Segment Notes:			
This segment is used to indicate the number of units to which the dangerous goods measurements apply.			
Example: EQN+1:2'			

## 5. Segments Layout

Segment number: 38

<b>SG35</b>	- C	999 - EQD-MEA-DIM-SEL-SG37			
<b>EQD</b>	- M	1 - Equipment details			
Function:					
To identify a unit of equipment.					
	EDIFACT	GS1	*	Description	
8053 Equipment type code qualifier	M an..3	<b>M</b>		CN = Container PA = Pallet UL = ULD (Unit load device) BPN = Box pallet non exchangeable EFP = Exchangeable EUR flat pallet	
C237 EQUIPMENT IDENTIFICATION	C	<b>R</b>			
8260 Equipment identifier	C an..17	<b>O</b>			
1131 Code list identification code	C an..17	<b>O</b>			
3055 Code list responsible agency code	C an..3	<b>D</b>		9 = GS1	
3207 Country name code	C an..3	<b>O</b>			
C224 EQUIPMENT SIZE AND TYPE	C	<b>O</b>			
8155 Equipment size and type description code	C an..10	<b>O</b>		6 = Pressurized tank 21 = Container IC 20 ft.	
1131 Code list identification code	C an..17	<b>O</b>			
3055 Code list responsible agency code	C an..3	<b>D</b>			
8154 Equipment size and type description	C an..35	<b>O</b>			
8077 Equipment supplier code	C an..3	<b>O</b>		1 = Shipper supplied 2 = Carrier supplied	
8249 Equipment status code	C an..3	<b>O</b>			
8169 Full or empty indicator code	C an..3	<b>O</b>		4 = Empty 5 = Full	
Segment Notes:					
This segment is used to indicate the units of equipment which have been used for the transport of the goods items in the arriving consignment.					
Example: EQD+UL+45223'					

## 5. Segments Layout

Segment number: 39

<b>SG35</b>	- C	999 - EQD-MEA-DIM-SEL-SG37			
<b>MEA</b>	- C	9 - Measurements			
Function:					
To specify physical measurements, including dimension tolerances, weights and counts.					
	EDIFACT	GS1	*	Description	
6311 Measurement purpose code qualifier	M an..3	<b>M</b>	*	AAE = <b>Measurement</b>	
C502 MEASUREMENT DETAILS	C	<b>A</b>			
6313 Measured attribute code	C an..3	<b>A</b>		AAD = <b>Total gross weight</b> T = <b>Tare weight</b>	
6321 Measurement significance code	C an..3	<b>N</b>			
6155 Non-discrete measurement name code	C an..17	<b>O</b>			
6154 Non-discrete measurement name	C an..70	<b>N</b>			
C174 VALUE/RANGE	C	<b>R</b>			
6411 Measurement unit code	M an..3	<b>M</b>		KGM = <b>kilogram</b> TNE = <b>tonne (metric ton)</b>	
6314 Measurement value	C an..18	<b>O</b>			
6162 Range minimum value	C n..18	<b>O</b>			
6152 Range maximum value	C n..18	<b>O</b>			
6432 Significant digits quantity	C n..2	<b>N</b>			
7383 Surface or layer code	C an..3	<b>N</b>			
Segment Notes:					
This segment is used to specify the gross or tare weight of the equipment identified in the previous EQD segment.					
Example: MEA+AAE+AAD+KGM:622'					

## 5. Segments Layout

Segment number: 40

<b>SG35</b>	- C	999 - EQD-MEA-DIM-SEL-SG37		
<b>DIM</b>	- C	9 - Dimensions		
Function:				
To specify dimensions.				
	EDIFACT	GS1	*	Description
6145 Dimension type code qualifier	M an..3	<b>M</b>		9 = Off-standard dimension general 10 = External equipment dimension
C211 DIMENSIONS	M	<b>M</b>		
6411 Measurement unit code	M an..3	<b>M</b>		MTR = metre
6168 Length dimension value	C n..15	<b>O</b>		
6140 Width dimension value	C n..15	<b>O</b>		
6008 Height dimension value	C n..15	<b>O</b>		
Segment Notes:				
This segment is used to indicate the dimensions of the equipment identified in the EQD segment.				
Example: DIM+10+MTR:2;2:1'				

## 5. Segments Layout

Segment number: 41

<b>SG35</b>	- C	999 - EQD-MEA-DIM-SEL-SG37					
<b>SEL</b>	- C	99 - Seal number					
Function:							
To specify the seal number or a range of seal numbers.							
	EDIFACT	GS1	*	Description			
9308 Seal identifier	C an..35	<b>R</b>					
C215 SEAL ISSUER	C	<b>R</b>					
9303 Sealing party name code	C an..3	<b>R</b>		CA = <a href="#">Carrier</a> CU = <a href="#">Customs</a> SH = <a href="#">Shipper</a>			
1131 Code list identification code	C an..17	<b>O</b>					
3055 Code list responsible agency code	C an..3	<b>D</b>					
9302 Sealing party name	C an..35	<b>O</b>					
4517 Seal condition code	C an..3	<b>O</b>					
C208 IDENTITY NUMBER RANGE	C	<b>N</b>					
7402 Object identifier	M an..35						
7402 Object identifier	C an..35						
Segment Notes:							
This segment is used to specify a seal number for the equipment identified in the EQD segment.							
Example: SEL+96753+SH'							

## 5. Segments Layout

---

Segment number: 42

<b>SG35</b>	- C	999 - EQD-MEA-DIM-SEL-SG37		
<b>SG37</b>	- C	9 - NAD		
<b>NAD</b>	- M	1 - Name and address		
Function:				
To specify the name/address and their related function, either by C082 only and/or unstructured by C058 or structured by C080 thru 3207.				
		EDIFACT	GS1 *	Description
3035	Party function code qualifier	M an..3	<b>M</b>	CR = <a href="#">Empty equipment return party</a> CW = <a href="#">Equipment owner</a>
C082	PARTY IDENTIFICATION DETAILS	C	<b>A</b>	
3039	Party identifier	M an..35	<b>M</b>	For identification of parties it is recommended to use GLN - Format n13.
1131	Code list identification code	C an..17	<b>N</b>	
3055	Code list responsible agency code	C an..3	<b>R</b> *	9 = <a href="#">GS1</a>
C058	NAME AND ADDRESS	C	<b>O</b>	This composite may only be used to fulfill the requirements of directive 2003/58/EC, article 4.
3124	Name and address description	M an..35	<b>M</b>	
3124	Name and address description	C an..35	<b>O</b>	
3124	Name and address description	C an..35	<b>O</b>	
3124	Name and address description	C an..35	<b>O</b>	
3124	Name and address description	C an..35	<b>O</b>	
C080	PARTY NAME	C	<b>D</b>	
3036	Party name	M an..35	<b>M</b>	Party Name in clear text.
3036	Party name	C an..35	<b>O</b>	
3036	Party name	C an..35	<b>O</b>	
3036	Party name	C an..35	<b>O</b>	
3036	Party name	C an..35	<b>O</b>	
3045	Party name format code	C an..3	<b>O</b>	
C059	STREET	C	<b>D</b>	
3042	Street and number or post office box identifier	M an..35	<b>M</b>	Building Name/Number and Street
3042	Street and number or post office box identifier	C an..35	<b>O</b>	Name and/or P.O. Box
3042	Street and number or post office box identifier	C an..35	<b>O</b>	
3042	Street and number or post office box identifier	C an..35	<b>O</b>	
3164	City name	C an..35	<b>D</b>	City/Town, clear text.
C819	COUNTRY SUB-ENTITY DETAILS	C	<b>D</b>	
3229	Country sub-entity name code	C an..9	<b>O</b>	
1131	Code list identification code	C an..17	<b>O</b>	
3055	Code list responsible agency	C an..3	<b>O</b>	

## 5. Segments Layout

Segment number: 42

	EDIFACT	GS1	*	Description
code				
3228 Country sub-entity name	C an..70	<b>O</b>		County/State, clear text.
3251 Postal identification code	C an..17	<b>D</b>		Postal Code
3207 Country name code	C an..3	<b>D</b>		ISO 3166 two alpha code

### Segment Notes:

This segment is used to specify the equipment owner, pick up or drop off addresses for the equipment specified in the EQD segment.

### Example:

NAD+CR+3323456007896::9'

### Dependency Notes:

The following composites and data elements are only used when a coded name and address can not be used.

The affected composites and data elements are as follows:

C080 - C059 - 3164 - C819 - 3251 - 3207

## 5. Segments Layout

Segment number: 43

UNT - M 1 - Message trailer				
Function:				
To end and check the completeness of a message.				
0074 Number of segments in the message		EDIFACT M n..6	GS1 *	Description
The total number of segments in the message is detailed here.				
0062 Message reference number		EDIFACT M an..14	GS1 *	Description
The message reference numbered detailed here should equal the one specified in the UNH segment.				
Segment Notes:				
This segment is used to end and check the completeness of a message.				
The UNT segment is a mandatory UN/EDIFACT segment. It must always be the last segment in the message.				
Example:				
UNT+43+ME000001'				

## 6. Examples

The following is an example of an arrival notice message from a carrier identified by GLN 5411234512309 to a consignee identified by GLN 5412345123453.

The arrival notice message is identified by number ARN-122 and sent on the 1st of November 2002 at 10am. The message reports the impending arrival of a consignment, identified with number 10203, at the place of delivery which is a location identified by GLN 5412345678908 by a truck from transport company ABC Express with license plate number ACX154. The estimated time of delivery is 2nd of November 2002 at 12.30pm. The disbursements for the consignment are Euros 250. The consignment consists of two goods items with total number of packages being 5, specified as follows:

The first goods item consists of 2 despatch unit of which the package type is returnable pallet and which are identified with EAN.UCC SSCC's: 354123450000000014, 354123450000000025.

The returnable pallets is said to contain 20 packages with grocery foodstuffs. The total gross weight of the 2 returnable pallets is 75 kg.

The second goods item consists of 3 despatch units of which the package type is a returnable pallet. The pallets with chilled foodstuff. The despatch units are identified with the EAN.UCC SSCC's: 354107380000001051, 354107380000001062, 354107380000001073.

The despatch units are transported at a temperature of 10 degrees Centigrade. Total gross weight of the 3 despatch units is 280 kg, however 1 despatch units weights 100, and the other 2 units weight each 90 kg.

UNH+ME002001+IFTMAN:D:01B:UN:EAN003'	Message header
BGM+781+ARN-122+9'	Arrival notice number ARN-122
DTM+137+200211011000:203'	Message date 11th November 2002 at 10:00
DTM+17+200211021230:203'	Estimated delivery date 2nd November 2002 at 12:30
MOA+50:250:EUR'	Amount disbursed 250 Euros
CNT+11:5'	Total number of packages 5
LOC+7+5412345678908'	Place of delivery identified by GLN 5412345678908
RFF+UCN+10203'	Unique consignment reference number 10203
TDT+20++30+31+:::ABC EXPRESS+++:::ACX154'	Transported by a truck from ABC Express plates: ACX154
NAD+CN+5412345123453::9'	Consignee identified by GLN 5412345123453
NAD+CA+5411234512309::9'	Carrier identified by GLN 5411234512309
GID+1+2:09::9+20:PK'	First occurrence 2 returnable pallets of 20 packages each
FTX+AAA+++GROCERY FOODSTUFFS'	Goods description in free text
MEA+WT+G+KGM:75'	The gross weight of the goods identified in the GID is 75 Kg.
PCI+33E+354123450000000014:354123450000000025'	The pallets are marked with the EAN.UCC Serial Shipping Container Code numbers 354123450000000014 and 354123450000000025
GID+2+3:09::9'	Second occurrence 3 returnable pallets

## 6. Examples

---

TMP+2+10.0:CEL'	The transport temperature is 10 degree Celsius
FTX+AAA+++CHILLED FOODSTUFFS'	Goods description in free text
MEA+WT+G+KGM:280'	The gross weight of the goods identified in the GID is 280 Kg.
MEA+WT+AAB+KGM:100'	The unit gross weight of the goods 100 Kg.
EQN+1'	The measurement apply to just one package
MEA+WT+AAB+KGM:90'	The unit gross weight of the goods 90 Kg
EQN+2'	The measurement apply to two packages
PCI+33E+354107380000001051:354107380000001062:	The pallets are marked with the EAN.UCC SSCC's
354107380000001073'	
UNT+25+ME002001'	Total number of segments in the message equals 25

Note :

The EDI interchange will include the UNB..UNZ segments and, if applicable, the UNG..UNE segments. (See part 1 section 5.7).

## 6. Examples

---